


User Manual

Using The Web Interface

The web interface has two interactable endpoints that can be used for testing purposes.




The image shows two dropdown menus from the web interface. The first dropdown is for the endpoint `POST /general-translation` with the label "General Translation". The second dropdown is for the endpoint `POST /translate-with-image` with the label "Translate With Image". Both dropdowns have a green header bar and a downward arrow on the right.

On either of these endpoints, POST requests can be sent via the browser to ensure that responses from external APIs are functioning properly. To send a sample request:

1. Open the drop-down for the desired request.
2. Click on the “Try it out” button located to the bottom right of the dropdown.
3. Edit the request body as desired.
4. Execute the request.

The response will be displayed under the “Responses” portion of the dropdown.



The image is a screenshot of the web interface for the `POST /general-translation` endpoint. The interface has a green header bar with the endpoint name and a "Cancel" button. Below the header, there is a "Parameters" section with the text "No parameters". The "Request body" section is labeled "required" and has a dropdown menu set to "application/json". Below this, there is a "Edit Value" section with a "Schema" tab. The "Schema" tab is active, showing a JSON schema:


```
{  "text": "string",  "source_language_code": "string",  "target_language_code": "string"}
```

. At the bottom of the interface, there is a blue "Execute" button.

Responses		
Code	Description	Links
200	Successful Response Media type application/json Controls Accept header. Example Value Schema <pre>"string"</pre>	No links
422	Validation Error Media type application/json Example Value Schema <pre>{ "detail": [{ "loc": ["string", 0], "msg": "string", "type": "string" }] }</pre>	No links

Using the Headset

On the headset UI, there will be two buttons, and three windows by default:



The leftmost button will state “EN -> ES” by default. This button controls the language transcribed in the bottom left box and the target translation / context language in the top and bottom right box. Using **hand tracking** or the **controller** the translation direction can

be changed by pushing the button, toggling the text between “EN -> ES” and “ES -> EN”, which are English to Spanish and Spanish to English respectively. The context box can be disabled by pushing the “Context” button in the same manner the language button is pushed.